
## **Table of Contents**

Backups	3
Configuration	3
Enable DB backup	
Enable FS backup	
Remote server for storing backups settings	
Saving changes	
Data recovery	
Restoring DB from backup	
Restoring FS from backup	

# **Backups**

Starting with version 2.25.9, the function of backup DB and FS has appeared. By enabling the function, you can configure the frequency of copying, storage duration, as well as export via SCP to a remote storage.


Move to the DB and FS settings section, open the Administrator menu item, section **«Backup settings»**.



# Configuration

#### **Enable DB backup**

To enable DB backup, select "Enabled".



Specify the following settings

- BACKUP DB ENABLED enable DB backup. (Default value is Disabled)
- BACKUP DB INTERVAL MINUTES backup DB time interval, minutes. (Default value is 1440)
- BACKUP\_DB\_PATH backup DB save path. (Default path is /var/dpiui2\_backup/db)
- BACKUP\_DB\_DELETE\_OLD\_INTERVAL\_MINUTES delete old DB backups interval, minutes. (Default value is 0)



When set to "O", old backups will not be deleted.

#### **Enable FS backup**



FS backup include .env files and folder contents /var/dpiui2/backend/storage

To enable FS backup, select "Enabled".



Specify the following settings

- BACKUP FS ENABLED enable FS backup. (Default value is Disabled)
- BACKUP\_FS\_INTERVAL\_MINUTES backup FS time interval, minutes. (Default value is 1440)
- BACKUP\_FS\_PATH backup FS save path. (Default path is /var/dpiui2\_backup/fs)
- BACKUP\_FS\_DELETE\_OLD\_INTERVAL\_MINUTES delete old FS backups interval, minutes. (Default value is 0)



When set to "O", old backups will not be deleted.

#### Remote server for storing backups settings

- **BACKUP\_SCP\_HOST** remote server host for storing backups.
- BACKUP\_SCP\_PORT remote server port for storing backups.
- BACKUP SCP USER backup storage username.

• BACKUP\_SCP\_PASSWORD - backup storage password.



SCP will use key authentication if no password is specified.

• BACKUP\_SCP\_DB\_PATH - backup DB remote path. (Default path is /var/dpiui2\_backup/db)



The folder must exist. The user must have access rights to this folder.


• BACKUP\_SCP\_FS\_PATH - backup FS remote path. (Default path is /var/dpiui2\_backup/fs)



The folder must exist. The user must have access rights to this folder.

### **Saving changes**

To save the edited parameters, click the **"Save"** button.



# **Data recovery**

To restore data from Backup, make sure that the dpiui2 server is installed and running.

## **Restoring DB from backup**

To restore the database, upload the database backup file to the dpiui2 server and run the following command in the terminal:

sh /var/www/html/dpiui2/backend/app\_bash/vas\_codebase/restore\_backup\_db.sh
dpiui2 dpiui2\_db\_backup.X.tar.gz

#### **Restoring FS from backup**



The file backup includes the **.env** file and **/var/dpiui2/backend/storage** directory contents.

To restore the dpiui2 FS upload the backup file to the dpiui2 server and run the following command:

sh /var/www/html/dpiui2/backend/app\_bash/vas\_codebase/restore\_backup\_fs.sh
dpiui2 dpiui2\_fs\_backup.X.tar.gz



After restoring the database and files, make sure everything works.