


Содержание

- 6 Backups 3
- Configuration 3
 - Enable DB backup* 3
 - Enable FS backup* 4
 - Remote server for storing backups settings* 5
 - Saving changes* 5
- Data recovery 6
 - Restoring DB from backup* 6
 - Restoring FS from backup* 6

6 Backups

Starting with version 2.25.9, the function of backup DB and FS has appeared. By enabling the function, you can configure the frequency of copying, storage duration, as well as export via SCP to a remote storage.

Move to the DB and FS settings section, open the Administrator menu item, section «**Backup settings**».



Configuration

Enable DB backup

To enable DB backup, select "**Enabled**".

Settings

Common
Jobs intervals and periods
QoE Stor: DB (Clickhouse) connection
QoE Stor: DB lifetime settings
QoE Stor: Discs settings
SMTP settings
System
DB (MySQL) connection
Push notifications settings
SSO authorization settings
Maps settings
VasCloud settings
Cluster settings
Backup settings

Backup settings

Enable DB backup (BACKUP_DB_ENABLED)

Disabled

Enabled

/var/dpiui2_backup/db

Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL)

0

Enable FS backup (BACKUP_FS_ENABLED)

Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)

24

Backup FS save path (BACKUP_FS_PATH)

/var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Specify the following settings

- **BACKUP_DB_ENABLED** - enable DB backup. (Default value is Disabled)
- **BACKUP_DB_INTERVAL_HOURS** - backup DB time interval, hours. (Default value is 24)
- **BACKUP_DB_PATH** - backup DB save path. (Default path is /var/dpiui2_backup/db)
- **BACKUP_DB_DELETE_OLD_INTERVAL** - delete old DB backups interval, hours. (Default value is 0)



When set to "0", old backups will not be deleted.

Enable FS backup



FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

To enable FS backup, select "**Enabled**".

QoE Stor: DB lifetime settings

QoE Stor: Discs settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Enable FS backup (BACKUP_FS_ENABLED)

Disabled

Enabled

/var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Remote server host for storing backups (BACKUP_SCP_HOST)

Remote server port for storing backups (BACKUP_SCP_PORT)

22

Specify the following settings

- **BACKUP_FS_ENABLED** - enable FS backup. (Default value is Disabled)
- **BACKUP_FS_INTERVAL_HOURS** - backup FS time interval, hours. (Default value is 24)
- **BACKUP_FS_PATH** - backup FS save path. (Default path is /var/dpiui2_backup/fs)
- **BACKUP_FS_DELETE_OLD_INTERVAL** - delete old FS backups interval, hours. (Default value is 0)



When set to "0", old backups will not be deleted.

Remote server for storing backups settings

- **BACKUP_SCP_HOST** - remote server host for storing backups.
- **BACKUP_SCP_PORT** - remote server port for storing backups.
- **BACKUP_SCP_USER** - backup storage username.
- **BACKUP_SCP_PASSWORD** - backup storage password.



SCP will use key authentication if no password is specified.

- **BACKUP_SCP_DB_PATH** - backup DB remote path. (Default path is /var/dpiui2_backup/db)



The folder must exist. The user must have access rights to this folder.


- **BACKUP_SCP_FS_PATH** - backup FS remote path. (Default path is /var/dpiui2_backup/fs)



The folder must exist. The user must have access rights to this folder.

Saving changes

To save the edited parameters, click the "**Save**" button.



Data recovery

To restore data from Backup, make sure that the server is installed and running [installed and running dpiui2](#).

Restoring DB from backup

To restore a database from a remote storage, run the following command in the terminal of the server where dpiui2 is installed:

```
gunzip < dpiui2_db_backup.X.sql.gz | mysql -u root -p dpiui2
```

Restoring FS from backup



The file backup includes the **.env** file and **/var/dpiui2/backend/storage** directory contents.

To restore files from a backup, run the following command:

```
sh /var/www/html/dpiui2/backend/app_bash/vas_codebase/restore_backup_fs.sh  
dpiui2 dpiui2_fs_backup.X.tar.gz
```



After restoring the database and files, make sure everything works.