

Содержание

Sharding configuration and QoE cluster setup	3
1. Cluster creation	3
2. Adding the cluster in GUI	4
1. Master node connection	4
2. Management via SSH	4
3. IPFIX receiver configuration	4

Sharding configuration and QoE cluster setup

QoE Stor can operate in sharding mode — horizontal cluster scaling, where parts of a single database are distributed across different shards (nodes). Sharding allows you to: 1. Distribute the IPFIX insertion load from multiple DPI units by spreading it across nodes. 2. Significantly accelerate report generation by leveraging the combined computational power of all nodes — reports are built in parallel and merged into a final result.

1. Cluster creation

To create a QoE Stor cluster, configure the cluster node settings on each node in the file `"/etc/clickhouse-server/config.d/qoestor-cluster-config.xml"`.

Edit the file on the first node:

```
<?xml version="1.0"?>
<yandex>
  <remote_servers>
    <qoestor_cluster>
      <shard>
        <replica>
          <host>127.0.0.1</host>
          <port>9000</port>
        </replica>
      </shard>
      <shard>
        <replica>
          <host>127.0.0.2</host>
          <port>9000</port>
        </replica>
      </shard>
      <shard>
        <replica>
          <host>127.0.0.3</host>
          <port>9000</port>
        </replica>
      </shard>
    </qoestor_cluster>
  </remote_servers>
</yandex>
```

Specify the IP address or hostname for each shard. Save the changes.

Copy the file to the remaining cluster nodes.

Restart the database with the ``fastor-db-restart`` command on each node. The cluster is now ready for operation.



Port 9000 must be open on all cluster nodes in the internal network between nodes.

2. Adding the cluster in GUI

1. Master node connection

Select which node will act as the master. Connect it in the GUI settings and enable cluster mode. See the screenshot below.



Port 8123 must be open on all cluster nodes.

2. Management via SSH

In the GUI section **Administrator / Equipment**, add all nodes for SSH management.



3. IPFIX receiver configuration

In the QoE Stor configuration, set up receivers for each node.



Reconfigure the DPI to send IPFIX to the corresponding QoE cluster nodes.