

# Содержание



First we select the protocols for Captive Portal availability in a separate class, as it is described in [Assignment of priorities](#). These protocols typically are http/https/dns.

```
bittorrent    0
http          8
https        8
dns           8
default      16
```

Next we create the configuration file `captive_portal.cfg`. It specifies the bandwidth limits in Captive Portal mode for each of 8 classes<sup>1)</sup>.

```
htb_root=rate 1mbit
htb_class0=rate 8bit ceil 8bit
htb_class1=rate 1mbit ceil 1mbit
htb_class2=rate 8bit ceil 8bit
htb_class3=rate 8bit ceil 8bit
htb_class4=rate 8bit ceil 8bit
htb_class5=rate 8bit ceil 8bit
htb_class6=rate 8bit ceil 8bit
htb_class7=rate 8bit ceil 8bit
```

`htb_root` - is the root class. It specifies the total bandwidth. The bandwidth is redistributed within this class

`rate` - is the lower bandwidth limit

`ceil` - is the upper bandwidth limit, that can be borrowed from the root class if available

We place a subscriber into Captive Portal when his account runs out of money:

```
fdpi_ctrl load --policing captive_portal.cfg --ip 192.168.0.1
fdpi_ctrl load --service 5 --ip 192.168.0.1
```

Here we unblock the subscriber upon a deposit to his account:

```
fdpi_ctrl load --policing rate_plan1.cfg --ip 192.168.0.1
fdpi_ctrl del --service 5 --ip 192.168.0.1
```

Future developments: a simplified (one step) method to put a subscriber into Captive Portal; support of various Captive Portal modes.

<sup>1)</sup>

[More details on bandwidth control](#)