Содержание

1 QoE Stor Configuration	3
QoE Stor Nodes	3
Configuration	3

1 QoE Stor Configuration

To go to the section, click the ADMINISTRATOR menu item, then click the QOE STOR CONFIGURATION menu item.

<	VAS Experts	=	Administrator > QoE Sto	or configuration											• •	• •	0
Se	arch	×	QoE Stor nodes <	Configuration													>
	SSG control	~	QoE in VAS Cloud	D Save E 🕑					ß		B 1	The form			4 Editor		
400	DODE			6¢ Settings	۲	Receivers											
800	PCR+ control	Ť		Receivers	+												
*	QoE analytics	~		Filtration		() Receiv	③ Portt	⑦ Port	() Rotati	() Rotati	() Rotati	⑦ Delay	() Queue	() insert	() Export	() DPI ID	•
0	VAS cloud services	~		Common	2	Netflow	top	1600	1	6	0	0	10	0	95.52.245	3	Û
				UIr settings	Ø	Netflow	tcp	15010	10	0	0	0	10	0		10	Û
-0-	Lowful interception	ř		FULLFLOW log settings	2	Netflow	top	1700	1	0	0	0	10	0		7	0
8	Administrator	^		CLICKSTREAM log settings	2	Clickstre	top	1601	1	0	0	40	10	0	95.52.245	3	Û
	Equipment			NAT log settings	Ø	Clickstre	tep	15011	12	0	0	400	10	0		10	Û
	Users			ONLINEFLOW log settings	Ø	Clickstre	top	1701	1	0	0	40	10	0		7	Û
	Roles																
	GUI configuration																
	dui logs																
	GUI update																
	QuE Stor configuration																
	QoE Stor logs																
>_	Hardware SSH terminal	~															
Vers	ion 2.23.7 B																

QoE Stor Nodes

This subsection contains the user's servers. To create or view a custom server that provides access to work in the "QoE Stor Configuration", you need to go to

Configuration

This subsection contains the following settings:

1. Receivers

To add it, click on the "**Add receiver**" button, fill in the following parameters in the window that opens:

Receiver type	_	Port type		_	Port	_
Netflow ~	œ	top	Ŭ	œ	0	œ
Rotate in minutes		Rotate in seconds			Rotate by flows	_
10	œ	0		œ	0	œ
Delay in seconds		Queue size			insert processes number	_
0	œ	10		œ	0	œ
Export		DPI ID				
10.0.0.2/9920/tep,10.0.0.3/3440	10	-1		Φ		

- The receiver type is selected from the drop-down list.
- **Rotation in minutes** is specified manually by the user. Implies the period of the receiver dump or the period of data loading into the databas.

<u>By default</u>: receiver type – Netflow, rotation – 10 min; receiver type – Clickstream, rotation - 12 min. <u>Note</u>: Do not change the value unnecessarily.

• **The delay in seconds** is specified manually by the user. Implies a delay in loading data from the database.

<u>By default</u>: receiver type – Netflow, delay – 0 sec; receiver type – Clickstream, delay - 400 sec. <u>Note</u>: Do not change the value unnecessarily.

- **Exporting** data to other servers. The server address is entered manually by the user.
- The port type is selected from the drop-down list.
- **Rotation in seconds** is specified manually by the user. Implies the period of the receiver dump or the period of data loading into the database.

<u>Note</u>: If this option is enabled, the rotation in minutes option is automatically disabled.

• **The queue size** is specified manually by the user. Implies the size of the receiver dump download queue.

Default value: 10.

Note: Do not change the value unnecessarily.

• **The DPI ID** specifies the DPI number. If the value "-1" is specified or not specified, then the DPI number is determined by the recipient's order in the list.

Note: Do not change the value unnecessarily.

• **The port** is a unique parameter and is entered manually by the user.

<u>By default</u>: receiver type - Netflow, port - 1500; receiver type - Clickstream, port - 1501.

- Rotation by the number of entries in the flow. It works simultaneously with the rotation parameter in minutes or seconds.
- The number of dump insertion processes. Without having to change the value.

To change the saved receiver, click on the "Change" button located to the left of each receiver. To remove the receiver, click on the "Delete" button located to the right of each receiver.

Ø	Netflow	top	15010	10	0	0	0	10	0	10	Û
Ø	Netflow	top	1700	1	0	0	0	10	0	7	Û

2. Filtering

All parameters are specified by selecting from the output list.

To explain the selection, you can click on the auxiliary button located to the right of each parameter.

Fitration		
Traffic direction definition (TRAFFIC_DIR_DEF_MODE) As is	~	•
Subscribers filter (SUBSCRIBER_FILTER_MODE) No filter	÷	0
Exclusions from the subscribers filter (SUBSCRIBER_EXCLUDE_MODE) No exclude	•	0
Subscribers bind mode (SUBSCRIBER_BIND_MODE)	v	0

 O - 'As is' - The direction of traffic does not change and is determined by the DPI 1 - 'By AS' - The direction of traffic is determined by the list of operators AS specified in the dictionary 2 - 'By CIDR' - The direction of traffic is determined by the CIDRs list specified in the dictionary 3 - 'By both: AS and CIDR' 4 - 'By any: AS or CIDR' 	Γ.	Traffic direction definition
 O - 'As is' - The direction of traffic does not change and is determined by the DPI 1 - 'By AS' - The direction of traffic is determined by the list of operators AS specified in the dictionary 2 - 'By CIDR' - The direction of traffic is determined by the CIDRs list specified in the dictionary 3 - 'By both: AS and CIDR' 4 - 'By any: AS or CIDR' 		Traffic direction definition
 1 - 'By AS' - The direction of traffic is determined by the list of operators' AS specified in the dictionary 2 - 'By CIDR' - The direction of traffic is determined by the CIDRs list specified in the dictionary 3 - 'By both: AS and CIDR' 4 - 'By any: AS or CIDR' 	1	0 - 'As is' - The direction of traffic does not change and s determined by the DPI
 2 - 'By CIDR' - The direction of traffic is determined by the CIDRs list specified in the dictionary 3 - 'By both: AS and CIDR' 4 - 'By any: AS or CIDR' 	мł	I - 'By AS' - The direction of traffic is determined by the ist of operator's AS specified in the dictionary
3 - 'By both: AS and CIDR' 4 - 'By any: AS or CIDR'	ł	2 - 'By CIDR' - The direction of traffic is determined by the CIDRs list specified in the dictionary
4 - 'By any: AS or CIDR'	1	3 - 'By both: AS and CIDR'
		4 - 'By any: AS or CIDR'

3. General

Parameters are specified by selecting from the output list, URLs are entered manually by the user. To explain the selection, you can click on the auxiliary button located to the right of each parameter.

© Common		
QoE Stor outoupdote (ENABLE_AUTOUPDATE) Under construction!	•	Ð
Autoload of hosts (urls) categories dictionaries (URLS_CATEGORIES_DIC_AUTOLOAD_ENABLED) Enabled	÷	®
URL for downloading of hosts (urls) categories dictionaries (URLS_CATEGORIES_DIC_URL) https://cloud.vasexperts.ru/api/clsfr		0
Autoload AS numbers dictionary (ASNUM_DIC_AUTOLOAD_ENABLED) Enabled	v	0
Autoload protocols dictionary (PRTCLS_DIC_AUTOLCAD_ENABLED)	~	•
URL for downloading protocols dictionary (PRTCLS_DIC_URL) https://cloud.vasexperts.ru/api/prtcls		0
Autoload custom protocols dictionary (CUSTOM_PRTCLS_DIC_AUTOLOAD_ENABLED) Enabled	~	0
URL for downloading custom protocols dictionary (CUSTOM_PRTCLS_DIC_URL) https://cloud.vasexperts.ru/api/custom_prtcls/qoe/886888888/test	\$3	•

4. URL Settings All parameters are specified by selecting from the drop-down list. To explain the selection, you can click on the auxiliary button located to the right of each parameter.

5. FULLFLOW Log Settings All parameters are specified by selecting from the output list. To explain the selection, you can click on the auxiliary button located to the right of each parameter.

6. CLICKSTREAM Log Settings All parameters are specified by selecting from the drop-down list. To explain the selection, you can click on the auxiliary button located to the right of each parameter.

7. NAT Log Settings All parameters are specified by selecting from the output list. To explain the selection, you can click on the auxiliary button located to the right of each parameter.

To save the settings in the configuration, click on the **"Save"** button located on the left in the toolbar. To restart the configuration, click on the **"Restart"** button located in the toolbar. To update the settings, click on the **"Update"** button located in the toolbar.

