

Содержание

- 7 Backup auto restoration 3
 - Enable auto restoration DB from backups* 3
 - Enable auto restoration FS from backups* 4
 - Saving changes* 4


7 Backup auto restoration

Starting from version 2.25.13 there is a function to automatically restore FS and DB from backups [backups](#).




When automatic restore from backups is enabled, the dpiui2 server will work in replication mode (all kernel processes will be disabled).

Move to the DB and FS settings section, open the Administrator menu item, section «**Backup auto restoration settings**».



Enable auto restoration DB from backups

To enable auto restoration DB from backups, select "**Enabled**"



Specify the following settings

- **BACKUP_RESTORATION_DB_ENABLED** - enable auto restoration DB from backups. (Default values is Disabled)
- **BACKUP_RESTORATION_DB_FOLDER** - folder path with DB backups.

Enable auto restoration FS from backups

To enable auto restoration FS from backups, select "**Enabled**"

The screenshot shows the 'Backup auto restoration settings' form. The left sidebar contains a list of settings: Common, Jobs intervals and periods, QoE Stor: DB (Clickhouse) connection, QoE Stor: DB lifetime settings, QoE Stor: Discs settings, SMTP settings, System, and DB (MySQL) connection. The main form area has three settings: 'Enable DB auto restoration from backup (BACKUP_RESTORATION_DB_ENABLED)', 'DB backup folder (BACKUP_RESTORATION_DB_FOLDER)', and 'Enable FS auto restoration from backup (BACKUP_RESTORATION_FS_ENABLED)'. The third setting has a dropdown menu open, showing 'Disabled' and 'Enabled' options. A green arrow points to the 'Enabled' option. Another green arrow points to the 'DB (MySQL) connection' setting in the left sidebar.



FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

Укажите следующие настройки

- **BACKUP_RESTORATION_FS_ENABLED** - enable auto restoration FS from backups. (Default values is Disabled)
- **BACKUP_RESTORATION_FS_FOLDER** - folder path with FS backups.

Saving changes

To save the edited parameters, click the "**Save**" button.

VAS Experts

Администратор > Конфигурация GUI

Поиск

- Управление DPI
- Управление PCRF
- QoS аналитика
- Сервисы VAS cloud
- Законный перехват
- Классификатор
- Администратор
 - Оборудование
 - Пользователи
 - Роли
 - Конфигурация GUI
 - Логи GUI
 - Обновление GUI
 - Конфигурация QoS Stor
 - Логи QoS Stor
- SSH терминал устройства

Версия 2.23.3 B

Настройки

Общие

Интервалы джобов

QoS Stor: Соединение с БД (Clickhouse)

QoS Stor: Настройки времени жизни БД

QoS Stor: Настройки дисков

Настройки SMTP

Системные

Подключение к БД MySQL

Настройки UI

Настройки пуш-нотификаций

Законный перехват

Настройки SSO-авторизации

Настройки карты

Настройки VaaSCloud

Настройки кластера

Настройки резервного копирования

Настройки авто восстановления из резервных копий

Настройки авто восстановления из резервных копий

Включить авто восстановление БД из резервных копий (BACKUP_RESTORE_DB_ENABLED)

Включено

Папка с резервными копиями БД (BACKUP_RESTORE_DB_FOLDER)

/var/dpiui2_backups/db

Включить авто восстановление файлов из резервных копий (BACKUP_RESTORE_FS_ENABLED)

Включено

Папка с резервными копиями файлов (BACKUP_RESTORE_FS_FOLDER)

/var/dpiui2_backups/fs



When automatic restore from backups is enabled, the dpiui2 server will work in replication mode (all kernel processes will be disabled).