

Содержание

2 Backups	3
Configuration	3

2 Backups

To go to the DB and FS settings section, open the Administrator menu item, section «**Backup settings**».

The screenshot shows the VAS Experts application interface. On the left, there's a sidebar with various menu items under 'Administrator'. A green arrow points from the 'Administrator' heading down to 'GUI configuration', which is highlighted with a green box. Another green arrow points from 'GUI configuration' down to 'Cluster settings', which is also highlighted with a green box. Within 'Cluster settings', 'Backup settings' is specifically highlighted with a green box and has a green arrow pointing to it. The main panel displays several configuration options related to backup settings, such as 'Enable DB backup (BACKUP_DB_ENABLED)', 'Backup DB time interval, hours (BACKUP_DB_INTERVAL_HOURS)', and 'Backup DB save path (BACKUP_DB_PATH)'. At the bottom left, it says 'Version 2.25.9 B'.

Configuration

Enable DB backup

To enable DB backup, select "**Enabled**".

This screenshot shows the 'Настройки резервного копирования' (Backup settings) screen. On the left, there's a sidebar with various configuration sections like 'Настройки SMTP', 'Системные', 'Подключение к БД MySql', etc. On the right, there are several configuration fields. One of them, 'Включение резервного копирования файлов (BACKUP_FS_ENABLED)', has a dropdown menu open with two options: 'Отключено' (Disabled) and 'Включено' (Enabled). A green arrow points to the 'Включено' option. Other fields shown include 'Время удаления старых бэкапов БД, часы (BACKUP_DB_DELETE_OLD_INTERVAL)' and 'Время удаления старых бэкапов файлов, часы (BACKUP_FS_DELETE_OLD_INTERVAL)'.

Specify the following settings

- **Backup DB time interval, hours.** (Default value - 24)
- **Backup DB save path.** (Default path: /var/dpiui2_backup/db)

- **Delete old DB backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

Enable FS backup



FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

To enable FS backup, select "**Enabled**".

Настройки SMTP
Системные
Подключение к БД MySql
Настройки пуш-нотификаций
Настройки SSO-авторизации
Настройки карты
Настройки VosCloud
Настройки кластера
Настройки резервного копирования

Время удаления старых бэкапов БД, часы (BACKUP_DB_DELETE_OLD_INTERVAL)
0

Включение резервного копирования файлов (BACKUP_FS_ENABLED)
Включено

Отключено
Включено ←

/var/dpiui2_backup/fs

Время удаления старых бэкапов файлов, часы (BACKUP_FS_DELETE_OLD_INTERVAL)
0

Specify the following settings

- **Backup FS time interval, hours.** (Default value - 24)
- **Backup FS save path.** (Default path: /var/dpiui2_backup/fs)
- **Delete old FS backups interval, hours.** (Default value - 0)



>When set to "0", old backups will not be deleted.

Remote server for storing backups settings

- **Remote server host for storing backups.**
- **Remote server port for storing backups.**
- **Backup storage username.**
- **Backup storage password.**



SCP will use key authentication if no password is specified.

- **Backup DB remote path.** (Default path: /var/dpiui2_backup/db)



The folder must exist. The user must have access rights to this folder.

- **Backup FS remote path.** (Default path: /var/dpiui2_backup/fs)



The folder must exist. The user must have access rights to this folder.

Saving changes

To save the edited parameters, click the "**Save**" button.

Подключение к БД MySql
Настройки пуш-нотификаций
Настройки SSO-авторизации
Настройки карты
Настройки VasCloud
Настройки кластера
Настройки резервного копирования

Включение резервного копирования файлов (BACKUP_FS_ENABLED)

Отключено ← Включено →

/var/dpiui2_backup/fs

Время удаления старых бэкапов файлов, часы (BACKUP_FS_DELETE_OLD_INTERVAL)
0