


# Содержание

|                     |   |
|---------------------|---|
| 2 Backups .....     | 3 |
| Configuration ..... | 3 |



## 2 Backups

To go to the DB and FS settings section, open the Administrator menu item, section «**Backup settings**».



## Configuration

### Enable DB backup

To enable DB backup, select "**Enabled**".

Settings

Common  
Jobs intervals and periods  
QoE Stor: DB (Clickhouse) connection  
QoE Stor: DB lifetime settings  
QoE Stor: Discs settings  
SMTP settings  
System  
DB (MySQL) connection  
Push notifications settings  
SSO authorization settings  
Maps settings  
VasCloud settings  
Cluster settings  
Backup settings

Backup settings

Enable DB backup (BACKUP\_DB\_ENABLED)

Disabled

Enabled

/var/dpiui2\_backup/db

Delete old DB backups interval, hours (BACKUP\_DB\_DELETE\_OLD\_INTERVAL)

0

Enable FS backup (BACKUP\_FS\_ENABLED)

Backup FS time interval, hours (BACKUP\_FS\_INTERVAL\_HOURS)

24

Backup FS save path (BACKUP\_FS\_PATH)

/var/dpiui2\_backup/fs

Delete old FS backups interval, hours (BACKUP\_FS\_DELETE\_OLD\_INTERVAL)

0

Specify the following settings

- **Backup DB time interval, hours.** (Default value - 24)
- **Backup DB save path.** (Default path: /var/dpiui2\_backup/db)
- **Delete old DB backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

## Enable FS backup



FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

To enable FS backup, select "**Enabled**".

QoE Stor: DB lifetime settings

QoE Stor: Discs settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Enable FS backup (BACKUP\_FS\_ENABLED)

Disabled

Enabled

/var/dpiui2\_backup/fs

Delete old FS backups interval, hours (BACKUP\_FS\_DELETE\_OLD\_INTERVAL)

0

Remote server host for storing backups (BACKUP\_SCP\_HOST)

Remote server port for storing backups (BACKUP\_SCP\_PORT)

22

Specify the following settings

- **Backup FS time interval, hours.** (Default value - 24)

- **Backup FS save path.** (Default path: /var/dpiui2\_backup/fs)
- **Delete old FS backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

### Remote server for storing backups settings

- **Remote server host for storing backups.**
- **Remote server port for storing backups.**
- **Backup storage username.**
- **Backup storage password.**



SCP will use key authentication if no password is specified.

- **Backup DB remote path.** (Default path: /var/dpiui2\_backup/db)



The folder must exist. The user must have access rights to this folder.

- **Backup FS remote path.** (Default path: /var/dpiui2\_backup/fs)



The folder must exist. The user must have access rights to this folder.

### Saving changes

To save the edited parameters, click the "**Save**" button.

- Search ✕
- SSG control
  - PCRf control
  - QoE analytics
  - VAS cloud services
  - Administrator
    - Equipment
    - Users
    - Roles
    - GUI configuration
    - GUI logs
    - GUI update
    - QoE Stor configuration
    - QoE Stor logs
  - Hardware SSH terminal

- ⚙️ Settings
  - Common
  - Jobs intervals and periods
  - QoE Stor: DB (Clickhouse) connection
  - QoE Stor: DB lifetime settings
  - QoE Stor: Disos settings
  - SMTP settings
  - System
  - DB (MySQL) connection
  - Push notifications settings
  - SSO authorization settings
  - Maps settings
  - VasCloud settings
  - Cluster settings
  - Backup settings

🔄
📄 The form
🛠️ Editor

### Backup settings

|                                                                       |                                     |   |
|-----------------------------------------------------------------------|-------------------------------------|---|
| Enable DB backup (BACKUP_DB_ENABLED)                                  | <input checked="" type="checkbox"/> | 🔗 |
| Backup DB time interval, hours (BACKUP_DB_INTERVAL_HOURS)             | 24                                  | 🔗 |
| Backup DB save path (BACKUP_DB_PATH)                                  | /var/dpiu2_backup/db                | 🔗 |
| Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL) | 0                                   | 🔗 |
| Enable FS backup (BACKUP_FS_ENABLED)                                  | <input checked="" type="checkbox"/> | 🔗 |
| Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)             | 24                                  | 🔗 |
| Backup FS save path (BACKUP_FS_PATH)                                  | /var/dpiu2_backup/ffs               | 🔗 |
| Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL) | 0                                   | 🔗 |
| Remote server host for storing backups (BACKUP_SCP_HOST)              |                                     | 🔗 |
| Remote server port for storing backups (BACKUP_SCP_PORT)              | 22                                  | 🔗 |
| Backup storage username (BACKUP_SCP_USER)                             |                                     | 🔗 |
| Backup storage password (BACKUP_SCP_PASSWORD)                         |                                     | 🔗 |