


Содержание

2 Backups	3
Configuration	3

2 Backups

Move to the DB and FS settings section, open the Administrator menu item, section «**Backup settings**».



Configuration

Enable DB backup

To enable DB backup, select "**Enabled**".

Settings

Common
Jobs intervals and periods
QoE Stor: DB (Clickhouse) connection
QoE Stor: DB lifetime settings
QoE Stor: Discs settings
SMTP settings
System
DB (MySQL) connection
Push notifications settings
SSO authorization settings
Maps settings
VasCloud settings
Cluster settings
Backup settings

Backup settings

Enable DB backup (BACKUP_DB_ENABLED)

Disabled

Enabled

/var/dpiui2_backup/db

Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL)

0

Enable FS backup (BACKUP_FS_ENABLED)

Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)

24

Backup FS save path (BACKUP_FS_PATH)

/var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Specify the following settings

- **Backup DB time interval, hours.** (Default value - 24)
- **Backup DB save path.** (Default path: /var/dpiui2_backup/db)
- **Delete old DB backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

Enable FS backup



FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

To enable FS backup, select "**Enabled**".

QoE Stor: DB lifetime settings

QoE Stor: Discs settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Enable FS backup (BACKUP_FS_ENABLED)

Disabled

Enabled

/var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Remote server host for storing backups (BACKUP_SCP_HOST)

Remote server port for storing backups (BACKUP_SCP_PORT)

22

Specify the following settings

- **Backup FS time interval, hours.** (Default value - 24)

- **Backup FS save path.** (Default path: /var/dpiui2_backup/fs)
- **Delete old FS backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

Remote server for storing backups settings

- **Remote server host for storing backups.**
- **Remote server port for storing backups.**
- **Backup storage username.**
- **Backup storage password.**



SCP will use key authentication if no password is specified.

- **Backup DB remote path.** (Default path: /var/dpiui2_backup/db)



The folder must exist. The user must have access rights to this folder.

- **Backup FS remote path.** (Default path: /var/dpiui2_backup/fs)



The folder must exist. The user must have access rights to this folder.

Saving changes

To save the edited parameters, click the "**Save**" button.

Search

SSG control

PCRf control

QoE analytics

VAS cloud services

Administrator

Equipment

Users

Roles

GUI configuration

GUI logs

GUI update

QoE Stor configuration

QoE Stor logs

> Hardware SSH terminal

Version 2.25.9 B

Save

t1

Settings

Common

Jobs intervals and periods

QoE Stor: DB (Clickhouse) connection

QoE Stor: DB lifetime settings

QoE Stor: Disks settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Backup settings

Enable DB backup (BACKUP_DB_ENABLED)

Backup DB time interval, hours (BACKUP_DB_INTERVAL_HOURS)

24

Backup DB save path (BACKUP_DB_PATH)

/var/dpiu2_backup/db

Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL)

0

Enable FS backup (BACKUP_FS_ENABLED)

Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)

24

Backup FS save path (BACKUP_FS_PATH)

/var/dpiu2_backup/ffs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Remote server host for storing backups (BACKUP_SCP_HOST)

Remote server port for storing backups (BACKUP_SCP_PORT)

22

Backup storage username (BACKUP_SCP_USER)

Backup storage password (BACKUP_SCP_PASSWORD)