


# Table of Contents

<b>2 Backups</b> .....	3
<b>Configuration</b> .....	3



# 2 Backups

Move to the DB and FS settings section, open the Administrator menu item, section «**Backup settings**».



## Configuration

### Enable DB backup

To enable DB backup, select "**Enabled**".

Specify the following settings

- **Backup DB time interval, hours.** (Default value - 24)
- **Backup DB save path.** (Default path: /var/dpiui2\_backup/db)
- **Delete old DB backups interval, hours.** (Default value - 0)

 When set to "0", old backups will not be deleted.

**Enable FS backup**

 FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

To enable FS backup, select "**Enabled**".

Specify the following settings

- **Backup FS time interval, hours.** (Default value - 24)

- **Backup FS save path.** (Default path: /var/dpiui2\_backup/fs)
- **Delete old FS backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

### Remote server for storing backups settings

- **Remote server host for storing backups.**
- **Remote server port for storing backups.**
- **Backup storage username.**
- **Backup storage password.**



SCP will use key authentication if no password is specified.

- **Backup DB remote path.** (Default path: /var/dpiui2\_backup/db)



The folder must exist. The user must have access rights to this folder.

- **Backup FS remote path.** (Default path: /var/dpiui2\_backup/fs)



The folder must exist. The user must have access rights to this folder.

### Saving changes

To save the edited parameters, click the "**Save**" button.

- Search
- SSG control
- PCRf control
- QoE analytics
- VAS cloud services
- Administrator
  - Equipment
  - Users
  - Roles
  - GUI configuration
  - GUI logs
  - GUI update
  - QoE Stor configuration
  - QoE Stor logs
- Hardware SSH terminal

- Settings
  - Common
  - Jobs intervals and periods
  - QoE Stor: DB (Clickhouse) connection
  - QoE Stor: DB lifetime settings
  - QoE Stor: Disks settings
  - SMTP settings
  - System
  - DB (MySQL) connection
  - Push notifications settings
  - SSO authorization settings
  - Maps settings
  - VasCloud settings
  - Cluster settings
  - Backup settings

Save

Backup settings

Enable DB backup (BACKUP_DB_ENABLED)	<input type="checkbox"/>
Backup DB time interval, hours (BACKUP_DB_INTERVAL_HOURS)	24
Backup DB save path (BACKUP_DB_PATH)	/var/dpiu2_backup/db
Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL)	0
Enable FS backup (BACKUP_FS_ENABLED)	<input type="checkbox"/>
Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)	24
Backup FS save path (BACKUP_FS_PATH)	/var/dpiu2_backup/ffs
Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)	0
Remote server host for storing backups (BACKUP_SCP_HOST)	
Remote server port for storing backups (BACKUP_SCP_PORT)	22
Backup storage username (BACKUP_SCP_USER)	
Backup storage password (BACKUP_SCP_PASSWORD)	