


Содержание

- 2 Backups 3
- Configuration 3
 - Enable DB backup* 3
 - Enable FS backup* 4
 - Remote server for storing backups settings* 5
 - Saving changes* 5

2 Backups

Move to the DB and FS settings section, open the Administrator menu item, section «**Backup settings**».



Configuration

Enable DB backup

To enable DB backup, select "**Enabled**".

Settings

- Common
- Jobs intervals and periods
- QoE Stor: DB (Clickhouse) connection
- QoE Stor: DB lifetime settings
- QoE Stor: Discs settings
- SMTP settings
- System
- DB (MySQL) connection
- Push notifications settings
- SSO authorization settings
- Maps settings
- VasCloud settings
- Cluster settings
- Backup settings**

Backup settings

Enable DB backup (BACKUP_DB_ENABLED) 

Disabled

Enabled 

/var/dpiui2_backup/db

Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL) 0

Enable FS backup (BACKUP_FS_ENABLED) 

Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS) 24

Backup FS save path (BACKUP_FS_PATH) /var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL) 0

Specify the following settings

- **Backup DB time interval, hours.** (Default value - 24)
- **Backup DB save path.** (Default path: /var/dpiui2_backup/db)
- **Delete old DB backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

Enable FS backup



FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

To enable FS backup, select "**Enabled**".

QoE Stor: DB lifetime settings

QoE Stor: Discs settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Enable FS backup (BACKUP_FS_ENABLED) 

Disabled

Enabled 

/var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL) 0

Remote server host for storing backups (BACKUP_SCP_HOST)

Remote server port for storing backups (BACKUP_SCP_PORT) 22

Specify the following settings

- **Backup FS time interval, hours.** (Default value - 24)

- **Backup FS save path.** (Default path: /var/dpiui2_backup/fs)
- **Delete old FS backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

Remote server for storing backups settings

- **Remote server host for storing backups.**
- **Remote server port for storing backups.**
- **Backup storage username.**
- **Backup storage password.**



SCP will use key authentication if no password is specified.

- **Backup DB remote path.** (Default path: /var/dpiui2_backup/db)



The folder must exist. The user must have access rights to this folder.

- **Backup FS remote path.** (Default path: /var/dpiui2_backup/fs)



The folder must exist. The user must have access rights to this folder.

Saving changes

To save the edited parameters, click the "**Save**" button.

- Search ✕
- SSG control
 - PCRf control
 - QoE analytics
 - VAS cloud services
 - Administrator
 - Equipment
 - Users
 - Roles
 - GUI configuration
 - GUI logs
 - GUI update
 - QoE Stor configuration
 - QoE Stor logs
 - Hardware SSH terminal

Save

⌵

Settings

Common

Jobs intervals and periods

QoE Stor: DB (Clickhouse) connection

QoE Stor: DB lifetime settings

QoE Stor: Disos settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Backup settings

Enable DB backup (BACKUP_DB_ENABLED)

Backup DB time interval, hours (BACKUP_DB_INTERVAL_HOURS)

24

Backup DB save path (BACKUP_DB_PATH)

/var/dpiu2_backup/db

Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL)

0

Enable FS backup (BACKUP_FS_ENABLED)

Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)

24

Backup FS save path (BACKUP_FS_PATH)

/var/dpiu2_backup/ffs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Remote server host for storing backups (BACKUP_SCP_HOST)

Remote server port for storing backups (BACKUP_SCP_PORT)

22

Backup storage username (BACKUP_SCP_USER)

Backup storage password (BACKUP_SCP_PASSWORD)