


Содержание

- 2 Backups 3
- Configuration 3
 - Enable DB backup* 3
 - Enable FS backup* 4
 - Remote server for storing backups settings* 5
 - Saving changes* 5

2 Backups

Starting with version 2.25.9, the function of backup DB and FS has appeared. By enabling the function, you can configure the frequency of copying, storage duration, as well as export via SCP to a remote storage.

Move to the DB and FS settings section, open the Administrator menu item, section «**Backup settings**».



Configuration

Enable DB backup

To enable DB backup, select "**Enabled**".

Settings

Common
Jobs intervals and periods
QoE Stor: DB (Clickhouse) connection
QoE Stor: DB lifetime settings
QoE Stor: Discs settings
SMTP settings
System
DB (MySQL) connection
Push notifications settings
SSO authorization settings
Maps settings
VasCloud settings
Cluster settings
Backup settings

Backup settings

Enable DB backup (BACKUP_DB_ENABLED)

Disabled

Enabled

/var/dpiui2_backup/db

Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL)

0

Enable FS backup (BACKUP_FS_ENABLED)

Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)

24

Backup FS save path (BACKUP_FS_PATH)

/var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Specify the following settings

- **BACKUP_DB_ENABLED** - enable DB backup. (Default value - Disabled)
- **BACKUP_DB_INTERVAL_HOURS** - backup DB time interval, hours. (Default value - 24)
- **BACKUP_DB_PATH** - backup DB save path. (Default path: /var/dpiui2_backup/db)
- **BACKUP_DB_DELETE_OLD_INTERVAL** - delete old DB backups interval, hours. (Default value - 0)



When set to "0", old backups will not be deleted.

Enable FS backup



FS backup include **.env** files and folder contents **/var/dpiui2/backend/storage**

To enable FS backup, select "**Enabled**".

QoE Stor: DB lifetime settings

QoE Stor: Discs settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Enable FS backup (BACKUP_FS_ENABLED)

Disabled

Enabled

/var/dpiui2_backup/fs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Remote server host for storing backups (BACKUP_SCP_HOST)

Remote server port for storing backups (BACKUP_SCP_PORT)

22

Specify the following settings

- **BACKUP_FS_ENABLED** - **enable FS backup.** (Default value - Disabled)
- **BACKUP_FS_INTERVAL_HOURS** - **backup FS time interval, hours.** (Default value - 24)
- **BACKUP_FS_PATH** - **backup FS save path.** (Default path: /var/dpiui2_backup/fs)
- **BACKUP_FS_DELETE_OLD_INTERVAL** - **delete old FS backups interval, hours.** (Default value - 0)



When set to "0", old backups will not be deleted.

Remote server for storing backups settings

- **BACKUP_SCP_HOST** - **remote server host for storing backups.**
- **BACKUP_SCP_PORT** - **remote server port for storing backups.**
- **BACKUP_SCP_USER** - **backup storage username.**
- **BACKUP_SCP_PASSWORD** - **backup storage password.**



SCP will use key authentication if no password is specified.

- **BACKUP_SCP_DB_PATH** - **backup DB remote path.** (Default path: /var/dpiui2_backup/db)



The folder must exist. The user must have access rights to this folder.

- **BACKUP_SCP_FS_PATH** - **backup FS remote path.** (Default path: /var/dpiui2_backup/fs)



The folder must exist. The user must have access rights to this folder.

Saving changes

To save the edited parameters, click the "**Save**" button.

Search

SSG control

PCRf control

QoE analytics

VAS cloud services

Administrator

Equipment

Users

Roles

GUI configuration

GUI logs

GUI update

QoE Stor configuration

QoE Stor logs

> Hardware SSH terminal

Version 2.25.9.8

Save

Settings

Common

Jobs intervals and periods

QoE Stor: DB (Clickhouse) connection

QoE Stor: DB lifetime settings

QoE Stor: Disks settings

SMTP settings

System

DB (MySQL) connection

Push notifications settings

SSO authorization settings

Maps settings

VasCloud settings

Cluster settings

Backup settings

Backup settings

Enable DB backup (BACKUP_DB_ENABLED)

Backup DB time interval, hours (BACKUP_DB_INTERVAL_HOURS)

24

Backup DB save path (BACKUP_DB_PATH)

/var/dpiu2_backup/db

Delete old DB backups interval, hours (BACKUP_DB_DELETE_OLD_INTERVAL)

0

Enable FS backup (BACKUP_FS_ENABLED)

Backup FS time interval, hours (BACKUP_FS_INTERVAL_HOURS)

24

Backup FS save path (BACKUP_FS_PATH)

/var/dpiu2_backup/ffs

Delete old FS backups interval, hours (BACKUP_FS_DELETE_OLD_INTERVAL)

0

Remote server host for storing backups (BACKUP_SCP_HOST)

Remote server port for storing backups (BACKUP_SCP_PORT)

22

Backup storage username (BACKUP_SCP_USER)

Backup storage password (BACKUP_SCP_PASSWORD)