

# Содержание

- Raw Fullflow compression ..... 3
  - Configuration settings* ..... 3
  - Fullflow Raw Log Compression Logs* ..... 4



# Raw Fullflow compression


## Configuration settings

**Step 1.** Go to Administrator → GUI Configuration → QoE Stor: Raw Log aggregation settings.

Set the values for all three parameters.




It is recommended to set the "QoE Stor aggregation time interval in hours" setting to more than 2 hours.




**Step 2.** Go to Administrator → Configuration QoE Stor → Fullflow log settings.

Set the "Enable FULLFLOW log background compressing" setting to "Enabled".



## Fullflow Raw Log Compression Logs

Move: QoE analytics → Administrator → Tablesapce info → Aggregation raw logs fullflow info



The section that opens displays information about completed tasks for compressing the raw fullflow log with the ability to set a filter by time, as well as delete tasks.

Delete selected log Delete all logs 12

© Springer 2014

- [-] Addressspace info
- [-] Addressspace info
- [-] Partitions info
- [-] Caches info
- [-] Aggregated cell row (1)
- [-] Dictionary info